







How to Add Infinite Scroll to a Content List Template

Version 5

Published 10/15/2020 07:29 AM by [Grace Kamau](#) Last updated 5/11/2021 06:59 PM by [Grace Kamau](#)

Add infinite scroll to a Content List template to let people browse for more content without leaving the page.

Latest News

-  Open Enrollment Starts Today!
-  Superior Customer Service
-  How to Get Your Coworkers to Take Pride in Their Work
-  12 Reasons to Celebrate at Work
-  How to Get Coworkers to Read Your Emails
-  Can a Company's Voice Be Strong and Clear When the Leadership Isn't?

Edit Template

1. Click the gear icon > **Page Builder** > **Templates**.
2. In **Widget Type**, select **Content List**.
3. Click the template you want to base the infinite scroll template on.
4. Click the gear icon > **Clone**. In this example, we'll clone the [Icon List Template](#) .
5. Click **Yes**.
6. Update the **Template Name**, for example *Icon List with Scroll*.
7. Find the line starting with `` .
8. Add `id="ScrollContainer{{WidgetID}}"` after `ul` . (e.g. `<ul id="ScrollContainer{{WidgetID}}">`)
9. At the bottom of the template, add a new line then add the following code

9. At the bottom of the template, add a new line then add the following code.

```
 {{{ScriptBlock}}}
<style> #ScrollContainer{{{WidgetID}} { height: 230px; overflow: scroll; } </style>
```

10. Click **Save Template**.

Add the Widget to a Page

1. Click **System > Page Builder**.
2. Add or edit a Page Builder page.
3. Click **Widgets**.
4. Drag a **Content List** widget onto the page.
5. On the Content List widget, click the gear icon > **Edit properties**.
6. Configure the widget properties.
7. Set **Total items** to 8.
8. Click **Template**.
9. Select the template you created.
10. Click **Advanced**.
11. Check **Infinite scroll**.
12. Click **Save Widget**.
13. Click **Publish changes**.
14. Click **Go to page**.

Troubleshooting

If you can't scroll in the widget, you can adjust the widget height or increase the widget's total item setting to enable the scroll.

Option 1: Increase Total Items

1. Click the gear icon > **Page Builder**.
2. Edit the page.
3. On the Content List widget, click the gear icon > **Edit properties**
4. Set **Total items** to a bigger number.
5. Click **Save Widget**.
6. Click **Publish changes**.

7. Click **Go to page**.

Option 2: Adjust Widget Height

1. Click the gear icon > **Page Builder > Templates**.
2. In **Widget Type**, select **Content List**.
3. Click the template.
4. At the bottom of the template code, replace `230px` with a smaller number.
5. Click **Save Template**.